

DEVICE ID SWAP: FC Web

Overview

You can swap a new hardware device with an existing asset/vehicle on FC Web, in the event of a warranty swap or 3G hardware migration.

This allows you to assign a new FC hardware to an existing asset without losing access to the asset's previous data.

ACCESS NEW DEVICE SERIAL ID

Once a new device is added to your account, FC Web automatically generates an asset shell.

Follow the steps below to access the new device asset shell:

- 1. Log in to FC Web
- 2. From the main menu, select Manage
- 3. Click Assets
- 4. The new Device serial ID will be listed on the left hand side menu
- 5. Select the new Device ID to access the details

≡	Assets	Assets	Asset Typ	pes									
•	earch for Asset		۹ +	Assets							8	C	
Ite	ms Found: 68		_	GENERAL	VEHICLE INFORMATION		RULE ASSIGNME	INT	SENSORS	ADVANCED			
	000042006867 My Fleet (Default	}		Description* 000042006867				Related Ass	et				
~	000042008023 My Fleet (Default	}		Asset Type * My Fleet (Default)		12/50		Resource					
-	015405002028 My Fleet (Default	839)		Device ID 000042006867		×		Device Data Set	tings '				
-	040#4 Fastest in the We	s1		Work Schedule				Standard In	-Vehicle Setting	×			
-	202-285-7700 My Fleet (Default)		Default 24/7 Work Schedule		٠		Transfind	ler Enable/Disable				
-	352753094032 My Fleet (Default	479		Vision Dashcam				Transfinder	Client ld	0/100			
J	352753094052 Asset Trackers	303								07100			
	000000000000000000000000000000000000000	0.40											

Note: For newly added devices, the Description and Device ID fields in the asset shell display the Device serial ID, unless the asset Description is changed by the user.

DEVICE SWAP

Follow the steps below to perform the Device ID Swap with an existing asset:

- 6. Copy the new Device Serial ID from the new Asset shell
- 7. Now, select an existing asset from the left hand side menu you wish to assign the new device to
- 8. Click the **x** icon next to the **Device ID** field to remove the old device ID associated with the asset
- 9. Paste the copied Device serial ID of the new hardware in the **Device ID** field

S	earch for Asset 🍳 🕂	Assets		
Iter	ms Found: 68	GENERAL	VEHICLE INFORMATION	RULE ASSIGNMENT
-	000042006867 My Fleet (Default)	Description * 04044		Relate
-	000042008023 My Fleet (Default)	Asset Type '	t	Resource Kat B
4000	015405002028839 My Fleet (Default)	Device ID 000042006867		X Device D
-	04044 Fastest in the West	This device is already assigned current selection	to 000042006867. Upon save, it will be reassigned t	to the Stand
-	202-285-7700 My Fleet (Default)	Mon-Fri 8-5		- En.
4000	352753094032479 My Fleet (Default)	Vision Dashcam		Transf
.	352753094052303 Asset Trackers			
Bjel	352753094065248			

- A message will display to indicate that the device ID is already associated with another asset
- 11. Click the **Save** button on the top right hand corner of the page to assign this device to the current asset

Once assigned and saved, the new device ID will no longer display in the Device ID field of the previous asset shell.

- In order to remove assets not applicable to you, select the previous asset shell again (new device ID) from the left hand side menu
- 13. Click the Delete button



Quick Reference Card

		_					
Item	is Found: 68	GENERAL	VEHICLE INFORMATION	RULE ASSIGNMENT	SENSORS		Deli
	000042006867 My Fleet (Default)	Description * 000042006867		Related Asset		_	
			12 / 50				
anga.	000042008023 My Fleet (Default)	Asset Type* My Fleet (Default)	•	Resource			
anp	015405002028839 My Fleet (Default)	Device ID					
liaja I	04044 Fastest in the West	Device in		Device Data Settings			
asp	202-285-7700 My Fleet (Default)	Default 24/7 Work Schedule					